



O2x5xx Sensors Library for Python 3.x

Table of Contents

- O2x5xx Sensors Library for Python 3.x
 - Description
 - Features
 - Prerequisites
 - Installation
 - Examples
 - Usage
 - PCIC client
 - Function Description
 - class Client
 - `recv(number_bytes)`
 - `close()`
 - class PCICV3Client
 - `read_next_answer()`
 - `read_answer(ticket)`
 - `send_command(cmd)`
 - class O2x5xxDevice
 - `activate_application(number)`
 - `application_list()`
 - `upload_pcic_output_configuration(config)`
 - `retrieve_current_process_interface_configuration()`
 - `request_current_error_state()`
 - `request_current_error_state_decoded()`
 - `gated_software_trigger_on_or_off(state)`
 - `request_device_information()`

- `return_a_list_of_available_commands()`
- `request_last_image_taken(image_id)`
- `request_last_image_taken_deserialized(self, image_id, datatype)`
- `overwrite_data_of_a_string(container_id, data)`
- `read_string_from_defined_container(container_id)`
- `return_the_current_session_id()`
- `set_logic_state_of_a_id(io_id, state)`
- `request_state_of_a_id(io_id)`
- `turn_process_interface_output_on_or_off(state)`
- `request_current_decoding_statistics()`
- `execute_asynchronous_trigger()`
- `execute_synchronous_trigger()`
- `set_current_protocol_version(version)`
- `request_current_protocol_version()`
- `turn_state_of_view_indicator_on_or_off(state, duration)`
- `class ImageClient`
 - `number_images()`
 - `read_image_ids()`
 - `read_next_frames()`
 - `make_figure()`
- Unit Tests
- Source Styleguide

Description

A Python 3 library for ifm efector O2x5xx 2D sensors (O2D5xx / O2I5xx).

Contact

In case of any issues or if you want to report a bug please [contact our support team](#).

Features

- PCIC V3 client for result data transfer
- O2X5xxDevice client for PCIC command usage

Prerequisites

Usage of examples requires packages listed in the requirements.txt file. Install the package with

```
$ pip install -r requirements.txt
```

Installation

Install the package with

```
$ python setup.py install
```

Examples

For a quick start, go to the `examples` folder and run

```
$ python output_recorder.py 192.168.0.69 myFile.txt 3600
```

with your device's IP address to record the asynchronous PCIC output for 3600 seconds and save the output into myFile.txt

```
$ python image_viewer.py 192.168.0.69
```

to view the image(s) data coming from the camera (requires matplotlib). Each image will be show in an own window.

Usage

PCIC client

The library currently provides three basic clients:

A simple PCIC V3 client

- Create it with `pcic = o3d3xx.PCICV3Client("192.168.0.69", 50010)` providing the device's address and PCIC port.
- Send PCIC commands with e.g. `answer = pcic.sendCommand("G?")` . All asynchronous PCIC messages are discarded while waiting for the answer to the command.
- Read back the next PCIC for a particular ticket number. This can be used to read asynchronously sent results (ticket number "0000"):
`answer = pcic.readAnswer("0000")`

- Read back any answer coming from the device:

```
ticket, answer = pcic.readNextAnswer()
```

A simple O2x5xx client (inheriting PCIC V3 client)

- Create it with `device = o2x5xx.O2x5xxDevice("192.168.0.69", 50010)` providing the device's address and PCIC port.
- Send PCIC commands wrapped into functions with e.g. `answer = device.occupancy_of_application_list()` . All asynchronous PCIC messages are discarded while waiting for the answer to the command.
- Upload PCIC configurations with e.g. `device = o2x5xx.O2x5xxDevice("192.168.0.69", 50010)` The PCIC configuration is valid for the instanced device (session).
- Complete function documentation as docstring.

A PCIC client for asynchronous image retrieval (inheriting O2x5xx client)

- Create it with `image_viewer = o2x5xx.ImageClient("192.168.0.69", 50010)` .
- It configures a PCIC connection to receive all images from the application.
- Read back the next result (a list with header information and dictionary containing all the images) with `result = pcic.readNextFrame()`
- Read back the next result (a list with header information and all images with datatype `numpy.ndarray`) with `result = pcic.readNextFrame()`

Function Description

For a more detailed explanation of the function take a look on the docstring documentation for each function.

class Client

recv(number_bytes)

Read the next bytes of the answer with a defined length.

```
:param number_bytes: (int) length of bytes
:return: the data as bytearray
```

close()

Close the socket session with the device.

```
:return: None
```

class PCICV3Client (inheriting class Client)

read_next_answer()

Read next available answer.

:return: None

read_answer(ticket)

Read the next available answer with a defined ticket number.

:param ticket: (string) ticket number

:return: answer of the device as a string

send_command(cmd)

Send a command to the device with 1000 as default ticket number. The length and syntax of the command is calculated and generated automatically.

:param cmd: (string) Command which you want to send to the device.

:return: answer of the device as a string

class O2x5xxDevice (inheriting class PCICV3Client)

activate_application(number)

Activates the selected application.

:param number: (int) 2 digits for the application number as decimal value

:return: - * Command was successful

- ! Application not available

| <application number> contains wrong value

| External application switching activated

| Device is in an invalid state for the command, e.g. configuration mode

- ? Invalid command length

occupancy_of_application_list()

Requests the occupancy of the application list.

:return: Syntax: <amount><t><number active application><t> ... <number><t><number>

e.g. 015 15 01 02 03 04 05 06 07 08 09 10

- <amount> char string with 3 digits for the amount of applications
 saved on the device as decimal number

- <t> tabulator (0x09)

- <number active application> 2 digits for the active application
- <number> 2 digits for the application number
- ! Application not available
 - | <application number> contains wrong value
 - | External application switching activated
 - | Device is in an invalid state for the command, e.g. configuration mode
- ? Invalid command length

upload_pcic_output_configuration(config)

Uploads a Process interface output configuration lasting this session.

```
:param config: (dict) configuration data
:return: - * Command was successful
        - ! Error in configuration
          | Wrong data length
        - ? Invalid command length
```

retrieve_current_process_interface_configuration()

Retrieves the current Process interface configuration.

```
:return: Syntax: <length><configuration>
        - <length> 9 digits as decimal value for the data length
        - <configuration> configuration data
        - ? Invalid command length
```

request_current_error_state()

Requests the current error state.

```
:return: Syntax: <code>
        - <code> Error code with 8 digits as a decimal value. It contains leading zeros.
        - ! Invalid state (e.g. configuration mode)
        - ? Invalid command length
        - $ Error code unknown
```

request_current_error_state_decoded()

Requests the current error state and error message as a tuple.

```
:return: Syntax: [<code>,<error_message>]
        - <code> Error code with 8 digits as a decimal value. It contains leading zeros.
        - <error_message> The corresponding error message to the error code.
        - ! Invalid state (e.g. configuration mode)
        - ? Invalid command length
        - $ Error code unknown
```

gated_software_trigger_on_or_off(state)

Turn gated software trigger on or off.

```
:param state: (int) 1 digit
              "0": turn gated software trigger off
              "1": turn gated software trigger on
:return: - * Trigger could be executed
        - ! Invalid argument, invalid state, trigger already executed
        - ? Something else went wrong
```

request_device_information()

Requests device information.

```
:return: Syntax:
        <vendor><t><article number><t><name><t><location><t>
        <description><t><ip><subnet mask><t><gateway><t><MAC><t>
        <DHCP><t><port number>
        - <vendor>          IFM ELECTRONIC
        - <t>                Tabulator (0x09)
        - <article number>  e.g. 02D500
        - <name>             UTF8 Unicode string
        - <location>        UTF8 Unicode string
        - <description>     UTF8 Unicode string
        - <ip>              IP address of the device as ASCII character sting e.g. 192.168.0.69
        - <port number>     port number of the XML-RPC
        - <subnet mask>     subnet mask of the device as ASCIIe.g. 192.168.0.69
        - <gateway>         gateway of the device as ASCIIe.g 192.168.0.69
        - <MAC>             MAC address of the device as ASCIIe.g. AA:AA:AA:AA:AA:AA
        - <DHCP>            ASCII string "0" for off and "1" for on
```

return_a_list_of_available_commands()

Returns a list of available commands.

```
:return: - H?              show this list
        - t                execute Trigger
        - T?              execute Trigger and wait for data
        - g<state>         turn gated software trigger on or off
        - o<io-id><io-state> set IO state
        - O<io-id>?        get IO state
        - I<image-id>?     get last image of defined type
        - A?               get application list
        - p<state>         activate / deactivate data output
        - a<application number> set active application
        - E?               get last Error
        - V?               get current protocol version
        - v<version>       get protocol version
        - c<length of configuration file><configuration file>
                                configure process data formatting
        - C?               show current configuration
        - G?               show device information
        - S?               show statistics
```

- L? retrieves the connection id
- j<id><length><data> sets string data under specific ID
- J<id>? reads string defined under specific ID
- d<on-off state of view indicator><duration> turn the view indicators on (permanently or for a defined time) or off

request_last_image_taken(image_id)

Request last image taken.

```
:param image_id: (int) 2 digits for the image type
    1: all JPEG images
    2: all uncompressed images
:return: Syntax: <length><image data>
    - <length> (int) char string with exactly 9 digits as decimal number for the image data
    - <image data> (bytearray) image data / result data. The data is encapsulated in an image chunk
    - ! No image available
      | Wrong ID
    - ? Invalid command length
```

request_last_image_taken_deserialized(image_id, datatype)

Request last image taken deserialized in image header and image data. Image data can requested or decoded as ndarray datatype.

```
:param image_id: (int) 2 digits for the image type
    1: all JPEG images
    2: all uncompressed images
:param datatype: (str) image output as hex or ndarray datatype
    bytes: image(s) as bytes datatype
    ndarray: image(s) as ndarray datatype
:return: Syntax: [<header>,<image data>]
    - <header> (dict) header of the image deserialized as dict object
    - <image data> image data / result data. The data is encapsulated in an image chunk if bytes as datatype is selected.
    - ! No image available
      | Wrong ID
    - ? Invalid command length
```

overwrite_data_of_a_string(container_id, data)

Overwrites the string data of a specific (ID) string container used in the logic layer.

```
:param container_id: (int) number from 00 to 09
:param data: (string) string of a maximum size of 256 Bytes
:return: - * Command was successful
    - ! Invalid argument or invalid state (other than run mode)
      | Not existing element with input-container-ID in logic layer
    - ? Syntax error
```

read_string_from_defined_container(container_id)

— — — — —

Read the current defined string from the defined input string container.
The string is represented as byte array.

:param container_id: (int) number from 00 to 09
:return: Syntax: <length><data>
- <length>: 9 digits as decimal value for the data length
- <data>: content of byte array
- ! Invalid argument or invalid state (other than run mode)
 | Not existing element with input-container-ID in logic layer
- ? Syntax error

return_the_current_session_id()

Returns the current session ID.

:return: 3 digits with leading "0"

set_logic_state_of_a_id(io_id, state)

Sets the logic state of a specific ID.

:param io_id: (int) 2 digits for digital output
 1: IO1
 "02": IO2
:param state: (int) 1 digit for the state
 "0": logic state low
 "1": logic state high
:return: Syntax: <IO-ID><IO-state>
- <IO-ID> 2 digits for digital output
 "01": IO1
 "02": IO2
- <IO-state> 1 digit for the state
 "0": logic state low
 "1": logic state high
- ! Invalid state (e.g. configuration mode)
 | Wrong ID
 | Element PCIC Output not connected to DIGITAL_OUT element in logic layer
- ? Invalid command length

request_state_of_a_id(io_id)

Requests the state of a specific ID.

:param io_id: 2 digits for digital output
 "01": IO1
 "02": IO2
:return: Syntax: <IO-ID><IO-state>
- <IO-ID> 2 digits for digital output
 "01": IO1
 "02": IO2
- <IO-state> 1 digit for the state
 "0": logic state low

- "1": logic state high
- ! Invalid state (e.g. configuration mode)
 - | Wrong ID
 - | Element PCIC Output not connected to DIGITAL_OUT element in logic layer
- ? Invalid command length

turn_process_interface_output_on_or_off(state)

Turns the Process interface output on or off. Be aware that this modification only affects the own session and is not considered to be a global parameter.

```
:param state: (int) 1 digit
    0: deactivates all asynchronous output
    1: activates asynchronous result output
    2: activates asynchronous error output
    3: activates asynchronous error and data output
    4: activates asynchronous notifications
    5: activates asynchronous notifications and asynchronous result
    6: activates asynchronous notifications and asynchronous error output
    7: activates all outputs
:return: - * Command was successful
        - ! <state>: contains wrong value
        - ? Invalid command length
```

request_current_decoding_statistics()

Requests current decoding statistics.

```
:return: Syntax: <number of results><t><number of positive decodings><t><number of false
           decodings>
        - <t> tabulator (0x09)
        - <number of results> Images taken since application start. 10 digits decimal value w
          leading "0"
        - <number of positive decodings> Number of decodings leading to a positive result. 10
          decimal value with leading "0"
        - <number of false decodings> Number of decodings leading to a negative result. 10 di
          decimal value with leading "0"
        - ! No application active
```

execute_asynchronous_trigger()

Executes trigger. The result data is send asynchronously.
Only compatible with configured trigger source "Process Interface" on the sensor.

```
:return: - * Trigger was executed, the device captures an image and evaluates the result.
        - ! Device is busy with an evaluation
          | Device is in an invalid state for the command, e.g. configuration mode
          | Device is set to a different trigger source
          | No active application
```

execute_synchronous_trigger()

Executes trigger. The result data is send synchronously.
Only compatible with configured trigger source "Process Interface" on the sensor.

:return: - (str) decoded data output of process interface
- ! Device is busy with an evaluation
| Device is in an invalid state for the command, e.g. configuration mode
| Device is set to a different trigger source
| No active application

set_current_protocol_version(version)

Sets the current protocol version. The device configuration is not affected.

:param version: 2 digits for the protocol version. Only protocol version V3 is supported.
:return: - * Command was successful
- ! Invalid version
- ? Invalid command length

request_current_protocol_version()

Requests current protocol version.

:return: Syntax: <current version><empty><min version><empty><max version>
- <current version> 2 digits for the currently set version
- <empty> space sign 0x20
- <min/max version> 2 digits for the available min and max version that can be set

turn_state_of_view_indicator_on_or_off(state, duration)

Turn the view indicators on (permanently or for a defined time) or off.

Syntax: d<on-off state of view indicator><duration>

:param state: (int) duration time in seconds
0: turn the view indicators off
1: turn the view indicators on
:param duration: (int) duration time in seconds (parameter has no impact if you turn indicator
:return: - * Command was successful
- ! Invalid state (e.g. configuration mode)
| Wrong state
| Wrong duration
- ? Invalid command length

class ImageClient (inheriting class O2x5xxDevice)

number_images()

A function for which returns the number of images from application.

```
:return: (int) number of images
```

read_image_ids()

A function for reading the PCIC image output and parsing the image IDs. The image IDs are stored in property `self.image_ids`

```
:return: list of image ids
```

read_next_frames()

Function for reading next asynchronous frames.
Frames are stored in property self.frames

```
:return: None
```

make_figure()

Function for making figure object and using parsed image ID as subtitle.

```
:param idx: (int) list index of self.image.IDs property
```

e.g. `idx == 0` would read string value '2' from `self.image.IDs = ['`

```
:return: Syntax: [<fig>, <ax>, <im>]
```

- <fig>: matplotlib figure object
- <ax>: AxesSubplot instance of figure object
- <im>: AxesImage instance of figure object

Unit Tests

FW version: 1.22.9323

| O2D5xx | O2I5xx | tested function | comment |
|--------|--------|----------------------|---------|
| x | x | activate_application | - |
| x | x | application_list | - |

| O2D5xx | O2I5xx | tested function | comment |
|--------|--------|--------------------------------------------------|-----------------------------------------------------------------------|
| x | x | upload_pcic_output_configuration | - |
| x | x | retrieve_current_process_interface_configuration | - |
| x | x | request_current_error_state | - |
| x | x | request_current_error_state_decoded | - |
| x | x | gated_software_trigger_on_or_off | - |
| x | x | request_device_information | - |
| x | x | return_a_list_of_available_commands | - |
| x | x | request_last_image_taken | uncompressed images not available due to high data size with 5 images |
| x | x | request_last_image_taken_deserialized | - |
| x | x | overwrite_data_of_a_string | - |
| x | x | read_string_from_defined_container | - |
| x | x | return_the_current_session_id | - |
| x | x | set_logic_state_of_a_id | - |
| x | x | request_state_of_a_id | Reading io states requires element in logic layer |
| x | x | turn_process_interface_output_on_or_off | - |
| x | x | request_current_decoding_statistics | - |
| x | x | execute_asynchronous_trigger | - |
| x | x | execute_synchronous_trigger | - |
| x | x | set_current_protocol_version | - |
| x | x | request_current_protocol_version | - |
| x | x | turn_state_of_view_indicator_on_or_off | only available for O2I5xx sensors |

FW version: 1.22.9009

| O2D5xx | O2I5xx | tested function | comment |
|--------|--------|-----------------|---------|
|--------|--------|-----------------|---------|

| O2D5xx | O2I5xx | tested function | comment |
|--------|--------|--------------------------------------------------|--------------------------------------------------------------------------------|
| x | x | activate_application | - |
| x | x | application_list | - |
| x | x | upload_pcic_output_configuration | - |
| x | x | retrieve_current_process_interface_configuration | - |
| x | x | request_current_error_state | - |
| x | x | request_current_error_state_decoded | - |
| x | x | gated_software_trigger_on_or_off | - |
| x | x | request_device_information | - |
| x | x | return_a_list_of_available_commands | - |
| x | x | request_last_image_taken | uncompressed images not available due to high data size with 5 images |
| x | x | request_last_image_taken_deserialized | - |
| x | x | overwrite_data_of_a_string | - |
| x | x | read_string_from_defined_container | - |
| x | x | return_the_current_session_id | - |
| x | x | set_logic_state_of_a_id | - |
| x | x | request_state_of_a_id | Reading io states requires element in logic layer |
| x | x | turn_process_interface_output_on_or_off | - |
| x | x | request_current_decoding_statistics | - |
| x | x | execute_asynchronous_trigger | - |
| x | x | execute_synchronous_trigger | - |
| x | x | set_current_protocol_version | - |
| x | x | request_current_protocol_version | - |
| x | x | turn_state_of_view_indicator_on_or_off | only available for O2I5xx sensors |

Source README.md Styleguide

<https://github.com/amontalenti/elements-of-python-style/blob/master/README.md>