

O2x5xx Sensors Library for Python 3.x

Table of Contents

- O2x5xx Sensors Library for Python 3.x
 - Description
 - Features
 - Prerequisites
 - Installation
 - Examples
 - Usage
 - PCIC client
 - Function Description
 - class Client
 - recv(number bytes)
 - close()
 - class PCICV3Client
 - read_next_answer()
 - read answer(ticket)
 - send command(cmd)
 - class O2x5xxDevice
 - activate application(number)
 - application list()
 - upload pcic output configuration(config)
 - retrieve current process interface configuration()
 - request current error state()
 - request_current_error_state_decoded()
 - gated_software_trigger_on_or_off(state)

- request_device_information()
- return_a_list_of_available_commands()
- request_last_image_taken(image_id)
- request last image taken deserialized(self, image id, datatype)
- overwrite data of a string(container id, data)
- read string from defined container(container id)
- return the current session id()
- set logic state of a id(io id, state)
- request state of a id(io id)
- turn process interface output on or off(state)
- request_current_decoding_statistics()
- execute asynchronous trigger()
- execute synchronous trigger()
- set current protocol version(version)
- request current protocol version()
- turn state of view indicator on or off(state, duration)
- class ImageClient
 - number images()
 - read_image_ids()
 - read_next_frames()
 - make_figure()
- Unit Tests
- Source Styleguide

Description

A Python 3 library for ifm efector O2x5xx 2D sensors (O2D5xx / O2I5xx).

Contact

In case of any issues or if you want to report a bug please contact our support team.

Features

- · PCIC V3 client for result data transfer
- O2X5xxDevice client for PCIC command usage

Prerequisites

Usage of examples requires packages listed in the requirements.txt file. Install the packages with

```
$ pip install -r requirements.txt
```

You can also install the package offline with following command

```
$ pip install --no-index --find-links ./packages -r requirements.txt
```

Installation

You can install the package with

```
$ python setup.py install
```

Examples

For a quick start, go to the examples folder and run

```
$ python output_recorder.py 192.168.0.69 myFile.txt 3600
```

with your device's IP address to record the asynchronous PCIC output for 3600 seconds and save the output into myFile.txt

```
$ python output_recorder.py 192.168.0.69 myFile.txt -1
```

with your device's IP address to record the asynchronous PCIC output endless and save the output into myFile.txt

```
$ python image_viewer.py 192.168.0.69
```

to view the image(s) data coming from the camera (requires matplotlib). Each image will be show in an own window.

Usage

PCIC client

The library currently provides three basic clients:

A simple PCIC V3 client

- Create it with pcic = o3d3xx.PCICV3Client("192.168.0.69", 50010) providing the device's address and PCIC port.
- Send PCIC commands with e.g. answer = pcic.sendCommand("G?") . All asnychronous PCIC messages are discarded while waiting for the answer to the command.
- Read back the next PCIC for a particular ticket number. This can be used to read asynchronously sent results (ticket number "0000"):

```
answer = pcic.readAnswer("0000")
```

Read back any answer coming from the device:

```
ticket, answer = pcic.readNextAnswer()
```

A simple O2x5xx client (inheriting PCIC V3 client)

- Create it with device = o2x5xx.02x5xxDevice("192.168.0.69", 50010) providing the device's address and PCIC port.
- Send PCIC commands wrapped into functions with e.g. answer =
 device.occupancy_of_application_list() . All asynchronous PCIC messages are discarded while
 waiting for the answer to the command.
- Upload PCIC configurations with e.g. device = o2x5xx.02x5xxDevice("192.168.0.69", 50010) The PCIC configuration is valid for the instanced device (session).
- · Complete function documentation as docstring.

A PCIC client for asynchronous image retrieval (inheriting O2x5xx client)

- Create it with image_viewer = o2x5xx.ImageClient("192.168.0.69", 50010) .
- It configures a PCIC connection to receive all images from the application.
- Read back the next result (a list with header information and dictionary containing all the images) with
 result = pcic.readNextFrame()
- Read back the next result (a list with header information and all images with datatype numpy.ndarray)
 with result = pcic.readNextFrame()

Function Description

For a more detailed explanation of the function take a look on the docstring documentation for each function.

class Client

recv(number_bytes)

Read the next bytes of the answer with a defined length.

:param number_bytes: (int) length of bytes

:return: the data as bytearray

close()

Close the socket session with the device.

:return: None

class PCICV3Client (inheriting class Client)

read_next_answer()

Read next available answer.

:return: None

read_answer(ticket)

Read the next available answer with a defined ticket number.

:param ticket: (string) ticket number
:return: answer of the device as a string

send_command(cmd)

Send a command to the device with 1000 as default ticket number. The length and syntax of the command is calculated and generated automatically.

:param cmd: (string) Command which you want to send to the device.
:return: answer of the device as a string

class O2x5xxDevice (inheriting class PCICV3Client)

activate_application(number)

Activates the selected application.

occupancy_of_application_list()

```
Requests the occupancy of the application list.
```

upload_pcic_output_configuration(config)

```
Uploads a Process interface output configuration lasting this session.
```

retrieve_current_process_interface_configuration()

```
Retrieves the current Process interface configuration.
```

request_current_error_state()

- ! Invalid state (e.g. configuration mode)
- ? Invalid command length
- \$ Error code unknown

request_current_error_state_decoded()

Requests the current error state and error message as a tuple.

:return: Syntax: [<code>,<error_message>]

- <code> Error code with 8 digits as a decimal value. It contains leading zeros.
- <error_message> The corresponding error message to the error code.
- ! Invalid state (e.g. configuration mode)
- ? Invalid command length
- \$ Error code unknown

gated_software_trigger_on_or_off(state)

Turn gated software trigger on or off.

:param state: (int) 1 digit

"0": turn gated software trigger off "1": turn gated software trigger on

:return: - * Trigger could be executed

- ! Invalid argument, invalid state, trigger already executed
- ? Something else went wrong

request device information()

Requests device information.

:return: Syntax:

<vendor><t><article number><t><name><t><location><t> <description><t><ip><subnet mask><t><gateway><t><MAC><t>

<DHCP><t><port number>

- <vendor> IFM ELECTRONIC Tabulator (0x09) - <t>

- <article number> e.g. 02D500 - <name> UTF8 Unicode string - <location> UTF8 Unicode string
- <description> UTF8 Unicode string
TD address of the di

IP address of the device as ASCII character sting e.g. 192.168.ℓ - <ip>

return_a_list_of_available_commands()

Returns a list of available commands.

```
show this list
:return: - H?
         - t
                                     execute Trigger
         - T?
                                      execute Trigger and wait for data
         - T? execute Trigger and wait for data

- g<state> turn gated software trigger on or off

- o<io-id><io-state> set IO state
         - O<io-id>? get IO state
- I<image-id>? get last image of defined type
         - A?
                                     get application list
         A? get application listp<state> activate / deactivate data output
         - a<application number> set active application
         - E?
                                      get last Error
         - V?
                                       get current protocol version
         - v<version> get protocol version
         - c<length of configuration file><configuration file>
                                      configure process data formatting
                                       show current configuration
         - G?
                                     show device information
         - S?
                                      show statistics
         - L?
                                       retrieves the connection id
         - j<id><length><data> sets string data under specific ID
                                  reads string defined under specific ID
         - d<on-off state of view indicator><duration> turn the view indicators on
                                       (permanently or for a defined time) or off
```

request_last_image_taken(image_id)

request_last_image_taken_deserialized(image_id, datatype)

Request last image taken deserialized in image header and image data. Image data can requested or decoded as ndarray datatype.

in an image chunk if bytes as datatype is selected.

- ! No image available
 - | Wrong ID
- ? Invalid command length

overwrite_data_of_a_string(container_id, data)

Overwrites the string data of a specific (ID) string container used in the logic layer.

```
:param container_id: (int) number from 00 to 09
```

:param data: (string) string of a maximum size of 256 Bytes

:return: - * Command was successful

- ! Invalid argument or invalid state (other than run mode)
 - | Not existing element with input-container-ID in logic layer
- ? Syntax error

read_string_from_defined_container(container_id)

Read the current defined string from the defined input string container. The string is represented as byte array.

```
:param container_id: (int) number from 00 to 09
```

:return: Syntax: <length><data>

- <length>: 9 digits as decimal value for the data length
- <data>: content of byte array
- ! Invalid argument or invalid state (other than run mode)
 - | Not existing element with input-container-ID in logic layer
- ? Syntax error

return_the_current_session_id()

```
Returns the current session ID.
```

:return: 3 digits with leading "0"

set_logic_state_of_a_id(io_id, state)

```
Sets the logic state of a specific ID.
```

```
:param io_id: (int) 2 digits for digital output
```

1: I01 "02": I02

02 . 102

:param state: (int) 1 digit for the state

"0": logic state low
"1": logic state high

:return: Syntax: <IO-ID><IO-state>

- <IO-ID> 2 digits for digital output

"01": I01
"02": I02

- <IO-state> 1 digit for the state

```
"0": logic state low
"1": logic state high
- ! Invalid state (e.g. configuration mode)
    | Wrong ID
    | Element PCIC Output not connected to DIGITAL_OUT element in logic layer
- ? Invalid command length
```

request_state_of_a_id(io_id)

turn_process_interface_output_on_or_off(state)

Turns the Process interface output on or off. Be aware that this modification only affects the own session and is not considered to be a global parameter.

request_current_decoding_statistics()

```
Requests current decoding statistics.
```

- <t> tabulator (0x09)
- <number of results> Images taken since application start. 10 digits decimal value wi leading "0"
- <number of positive decodings> Number of decodings leading to a positive result. 10

- decimal value with leading "0"
- <number of false decodings> Number of decodings leading to a negative result. 10 dig
 decimal value with leading "0"
- ! No application active

execute_asynchronous_trigger()

Executes trigger. The result data is send asynchronously.

Only compatible with configured trigger source "Process Interface" on the sensor.

:return: - * Trigger was executed, the device captures an image and evaluates the result.

-! Device is busy with an evaluation

| Device is in an invalid state for the command, e.g. configuration mode

Device is set to a different trigger source

No active application

execute_synchronous_trigger()

Executes trigger. The result data is send synchronously.

Only compatible with configured trigger source "Process Interface" on the sensor.

:return: - (str) decoded data output of process interface

- ! Device is busy with an evaluation

Device is in an invalid state for the command, e.g. configuration mode

Device is set to a different trigger source

No active application

set_current_protocol_version(version)

Sets the current protocol version. The device configuration is not affected.

:param version: 2 digits for the protocol version. Only protocol version V3 is supported.

:return: - * Command was successful

- ! Invalid version
- ? Invalid command length

request_current_protocol_version()

Requests current protocol version.

:return: Syntax: <current version><empty><min version><empty><max version>

- <current version> 2 digits for the currently set version
- <empty> space sign 0x20
- <min/max version> 2 digits for the available min and max version that can be set

turn_state_of_view_indicator_on_or_off(state, duration)

Turn the view indicators on (permanently or for a defined time) or off.

class ImageClient (inheriting class O2x5xxDevice)

number_images()

```
A function for which returns the number of images from application.
```

read_image_ids()

:return: (int) number of images

```
A function for reading the PCIC image output and parsing the image IDs.

The image IDs are stored in property self.image_IDs

:return: list of image ids
```

read_next_frames()

```
Function for reading next asynchronous frames.

Frames are stored in property self.frames

:return: None
```

make_figure()

```
Function for making figure object and using parsed image ID as subtitle.

:param idx: (int) list index of self.image.IDs property

e.g. idx == 0 would read string value '2' from self.image.IDs = ['2

:return: Syntax: [<fig>, <ax>, <im>]

- <fig>: matplotlib figure object

- <ax>: AxesSubplot instance of figure object

- <im>: AxesImage instance of figure object
```

Unit Tests

You can run the tests with following command:

```
$ python .\test_pcic.py 192.168.0.69 1.27.9941 True
```

You can see the results of the tests in the log files stored in the folder tests/logs.

Source README.md Styleguide

https://github.com/amontalenti/elements-of-python-style/blob/master/README.md